

WP SOCIAL LOCKER USER'S GUIDE

WP Social Locker Documentation

WP Social Locker is a wordpress plugin designed to enable a lock system to your website contents. This plugin hides the content from visitors until your preferred settings are met. However, if the visitors would like to view the content immediately, they will need to click on any of the social buttons available.


TABLE OF CONTENTS

Title Page	1
Introductory Page	2
Table of Contents	3
How to Use WP Social Locker	4
How to Hide Specific Contents with WP Social Locker	16
How to Hide Entire Contents with WP Social Locker	17
How to Hide Video Contents with WP Social Locker	17
Settings of WP Social Locker	18
Table and Graph Stats of WP Social Locker	19


How to Use WP Social Locker

This guide assumes that you are already logged in to your wordpress admin area and that **WP Social Locker** has been successfully installed in your wordpress site.

1. Click the **WP Social Locker** menu in your wordpress admin dashboard to create a new social locker.



2. Click **Add New**.



Alternatively, you may also hover your mouse on the menu to display the options available. Then, click **Add Social Locker**.

Locker Design

Box Layout

Standard Center



Standard Left



Boxed Left



Boxed Right



Box Design


Theme 1



Theme 2



Theme 3



Theme 4



Button Design

Design 1



Design 2



Design 3



Design 4



Design 5



Design 6



Design 7



Design 8



Design 9



Design 10

Options

Close Link

On Off Set on to show close link

Close Link Position

Top Right Position of close link

Timer Interval

0 Set a value to using timer

Timer Position

Bottom Right Position of timer info

AJAX Content Load

On Off Set on to use ajax to load content

Mobile Support

On Off Set on to display locker in mobile

Highlight Effect

On Off Set on to use highlight effect

Hide for members

On Off Set on to hide locker for members


Alert Message

On Off Set on to show alert message

Set message in here

Preview

Note: It's just preview. The Locker and the social buttons don't work correctly in the admin area.



Publish


The **Locker Name** is where you will add a title that would enable you to distinguish one social locker from the other as your social lockers will increase.

Under the **Basic Option** tab is the **Locker Title** and **Locker Info**.

- **Locker Title.** This is the heading of the social locker the visitors will see when this goes live. You can leave this field empty depending on your preferences.
- **Locker Info.** This is the message of your social locker that goes below the locker header. In here you can add texts and multimedia messages depending on your preference.

The **Social Options** tab is where you can setup 7 social media accounts which will give your visitors the option not to comply on the settings you have set for them to view the content. Instead, they will have to like, tweet, follow, or share one of the social media accounts available.


You may drag the social media accounts to re-order them. Each social media account has the following settings (refer to the image below):

A screenshot of a settings form for a social media locker. It features three sections: 1. 'Available' with a toggle switch currently set to 'On' (green) and 'Off' (grey). Below it is the text 'Set Off to hide the Share Button.' 2. 'URL to share' with an empty text input field. Below it is the text 'Set any URL to share. Leave this field empty to use a current page.' 3. 'Button Title' with an empty text input field.


- **Available.** This is a switch that would trigger the activation of the social media buttons in your social locker. By default this is turned on.
- **URL to Share.** This field should be filled up with the url of which you would like the visitors to share when the button is clicked.
- **Button Title.** This will be the label of the social media button that the visitors will have to click to view the locked content.

The **Locker Design** tab is where you can customize the look and feel of your social lockers. Inside the tab are 3 other tabs to design the elements of the social locker which are as follows:


- **Box Layout.** There are 4 available layout options you can choose from on how you would like you social locker contents be displayed to your users. You can enlarge the images to preview on how it will make your social locker box look like by hovering your mouse over the options.
 - **Standard Center**




- **Standard Left**



- **Boxed Left**



- **Boxed Right**




- **Box Design.** There are 8 available box themes available for you to choose how you would like the social locker box to appear. Hover your mouse over the options to enlarge and preview the theme.


- **Theme 1**



- **Theme 2**




- **Theme 3**




- **Theme 4**




- **Theme 5**




- **Theme 6**



- **Theme 7**




- **Theme 8**




- **Button Design.** Select from 10 pre-made social media buttons you prefer to use and be displayed inside your social locker box. Enlarge the images to preview the buttons designs by hovering your mouse over the options.


○ **Design 1**



○ **Design 2**



○ **Design 3**



○ **Design 4**



○ **Design 5**




○ **Design 6**




○ **Design 7**



- **Design 8**



- **Design 9**




- **Design 10**



The **Options** tab is where you can configure settings to add functionality to your social locker.

- **Close Link.** This option adds a close icon in the social locker. This will enable the visitor to close the locker and view the locked content without the need to click any of the social media buttons.



- **Close Link Position.** This option enables you to choose from 4 different positions the close icons should be located: Top Right, Top Left, Bottom Right or Bottom Left.




- **Timer Interval.** This offers a text field that accepts a numerical value (in seconds) equivalent to the time period the content will be available for the visitor to access the hidden content.

- **Timer Position.** This option offers you the flexibility to choose from the 4 positions the timer should be located. You can have it positioned in Top Right, Top Left, Bottom Right or Bottom Left.


- **AJAX Content Load.** When the switched for this setting is turned on, the content will be loaded in advance so that the content will be completely unavailable to the user and hides it in the source code of the page. Contents will only be available once the visitor clicks any of the social media buttons. An important note to be reminded of is that although the process of locking/hiding the contents using this option is more secure, contents will be displayed slower as they have to be loaded when the visitor clicks any of the social media buttons.

- **Mobile Support.** Turn the switch of this option on if you would like the social locker to be displayed when a user is viewing your site through a mobile device. Turning it off would disable social locker.


- **Highlight Effect.** When this option's switch is turned on, it will set the start effect when the content is displayed to the user. Turning this off will disable the effect.



- **Hide for Members.** If you have this plugin installed in a membership site, then this option will give you the ability to automatically display the content by the social locker to the logged in members.



- **Alert Message.** This option enables you to create an alert message displayed to your user once they have successfully unlocked the content. It consists of a switch that enables or disables the function and the textfield where you will enter the alert message.




The **Preview** tab displays how your social locker looks when it goes live. Be reminded that this is for preview purposes only and that the buttons may work correctly while inside the wordpress admin area.

Lastly, the **Publish/Update** button found below the preview tab. The button will display the label **Publish** if this is a newly created social locker and **Update** if the social locker has already been published and is just currently edited.


How to Hide Specific Contents with WP Social Locker

This section of this guide assumes that you already have created at least one social locker.

1. Create a new page or post where you would like to insert the content to be hidden with WP Social Locker.
2. Click the Social Locker icon to display the option to add the social locker(s) created. Make sure that you have set your page or post editor in visual editor mode to access the icon otherwise it won't be accessible for use. Please refer to the image below.



3. Once the icon has been clicked, this will display a popup box where you can select the social locker of your choosing from the dropdown and click the **Add Social Locker** button to generate the shortcode.



4. In between the shortcode, enter the content you would like to be hidden or locked from your visitors. Please see example below:

```
[wp-sociallocker id="1"]
```

Enter the content you would like to be locked or hidden from your visitors.


```
[/wp-sociallocker]
```

5. Publish or update the page and see WP Social Locker in action.

How to Hide Entire Contents with WP Social Locker

This section of this guide assumes that you already have created at least one social locker.

1. Create or edit a post or a page where you would like to add WP Social Locker functionality.
2. From the **Post Locker** tab in your page or post editor is a dropdown listing the social lockers you have already created. Select one.




3. Publish or update the page/post to implement WP Social Locker.

How to Hide Video Contents with WP Social Locker

WP Social Locker is capable of hiding all contents including videos although there is a limitation that can only be overcome when using another plugin as plain embed codes are not read by the plugin. To do this:

1. Install [Youtube Embed Plus](#) plugin.
2. Add or edit a post or page you would like the video content to be hidden.
3. Click the WP Social Locker icon to add the social locker of your choice and generate the shortcode.
4. Insert the video code in between the shortcode just as shown in the sample below. Note that with Youtube Embed Plus, you are only required to enter the url of the video.



5. Publish or update the post or page to implement WP Social Locker.

Settings of WP Social Locker

The **Settings** section is designed to setup global options for WP Social Locker.




Facebook App ID. The facebook app ID is required in order to implement the like and share function of the facebook buttons. Please refer to and click this [link](#) to know more. By default, this field will use the App ID used by the developers.

Table and Graph Stats of WP Social Locker

The **Table and Graph Stats** section of WP Social Locker provides information regarding user interaction to the pages where you have WP Social Locker implemented. Data are in both tabular and graphical presentation for analysis convenience. Please refer to the images below for a preview on these sections.


Table Stats



The columns of the tabular presentation of data can be managed by clicking the social media buttons and options located on top of the table.



Graph Stats



For graph stats, you can display specific data on the graph by clicking on the 3 buttons on the top left portion of the page. You can choose either viewing the **Total** social interactions, **Detailed** social interactions or via **Helpers**.

You may as well configure the date range according to your choosing to check statistics of a specific time frame by using the **Date Range** option on the top right section of the page.